

Eduroam Setup - XP

Click Start and then Control Panel. With your mouse right button click wireless connection and open the Properties tab.

...



In the Wireless Network tab click Add.

🚣 Wireless Network Connection F	Wireless Network Connection Properties				
General Wireless Networks Advar	nced				
☑ Use <u>W</u> indows to configure my w	ireless network settings				
Available <u>n</u> etworks: To connect to, disconnect from, o about wireless networks in range,	r find out more information click the button below.				
	View Wireless Network	s			
Preferred networks: Automatically connect to available below:	networks in the order liste	ed			
	Move <u>u</u> p Move <u>d</u> ov	m			
Add Bemove	Properties				
Learn about setting up wireless nel configuration.	work Advance				
	OK Ca	incel			

•••

Configure as described below: Network name: eduroam Security type: WPA2 Encryption type: AES Click Next

Wireless network properties		
Association Authentication	Connection	
Network <u>n</u> ame (SSID):	eduroam	
Connect even if this n	etwork is not broadcasting	
This network requires a ke	ey for the following:	
Network <u>A</u> uthentication:	WPA2	
Data encryption:	AES	
Network <u>k</u> ey:		
Confirm network key:		
Key inde <u>x</u> (advanced):	1	
The key is provided fo	r me automatically	
This is a <u>c</u> omputer-to-cor access points are not us	mputer (ad hoc) network; wireless ed	
	OK Cancel	

In the tab Authentication

Untick "Authenticate as computer when computer information is available" Select Protected EAP (PEAP) and click Properties.

...

Wireless network properties			? ×		
Association	Authentication	Connect	ion		
Select this wireless Eth	option to provide hemet networks.	authentic	ated network	access for	
🔽 <u>E</u> nable	IEEE 802.1x auti	henticatio	n for this netw	vork	
EAP type:	Protected EAP	(PEAP)			-
				Properti	ies
Authen availab	ticate as <u>c</u> ompute le	er when c	omputer inforr	mation is	
Authen unavail	ticate as guest w able	hen user (or computer ir	nformation is	8
			OK	Ca	incel

In the Properties window, Untick Validate server certificate, Untick Enable Fast Reconnect

Protected EAP Properties
When connecting:
Connect to these servers:
Trusted <u>R</u> oot Certification Authorities:
 ABA.ECOM Root CA Autoridad Certificadora de la Asociacion Nacional del Notaria Autoridad Certificadora del Colegio Nacional de Correduria P. Baltimore EZ by DST Belgacom E-Trust Primary CA C&W HKT SecureNet CA Class A C&W HKT SecureNet CA Class B
Do not prompt user to authorize new servers or trusted certification authorities.
Select Authentication Method:
Secured password (EAP-MSCHAP v2)
OK Cancel

Click Configure and untick the check box.



•••

When asked type your username and password.

The username and password must be the same used to enter the Moodle/Intranet